


Instructions:

- 1) At start the software show a screen with the time remaining for trial.
For trial click Continue or click Register to buy.

The screenshot shows a software window titled "EBRcart2 - shareware". The window contains the following elements:

- A "Language" label at the top left.
- Text: "Version shareware" and "Time to trial is 30 days".
- A button labeled "LANGUAGE" next to the text "Change the language ==>".
- A progress bar labeled "Days remaining: 29".
- Three buttons: "Continue", "Register" (highlighted with a dashed border), and "Exit".
- A section titled "1. To buy click" with a "BUY" button.
- A section titled "2. To REGISTER inform:".
- Text: "Your e-mail address:" followed by an empty text input field.
- Text: "The serial number received:" followed by an empty text input field.
- A "Register" button next to the serial number input field.
- Footer text: "EBRaudio - suport@ebraudio.com".

2) In the first time, you need inform the configuration for channels and cue:



2.1 – Language: click to to change the language. Select a file with extension “.lng”. If your language doesn’t exist, create one, editing the file named “english.lng” and translating it. This file is located at “c:\program files\ebrcart2”

2.2 – AUDIO CARDS: you may have 1, 2 or 3 audio cards. Select one for each channel;

2.3 – FILES:


- **directory to record log file:** select a directory to record information about played audios.
- **Directory to scripts:** select a directory where you saved your scripts.

2.4 – FADES:

- **Fade-out time:** time of fade out an audio after press key stop;
- **Fade to talk time:** time to fade audios on channel 1/2 and use microphone or repeat.

2.5 – INTERFACE: hotkeys and trigger

- **Buttons with letters:** hotkeys with alphabetic key (A...X);
- **Buttons with function keys:** label buttons with F1...F12 and numeric key
- **Trigger by serial port (CTS):** trigger by serial (see interface)




contact closed = press space key over a cart

3) MENU

EBRcart has 6 pages (1,2,3,4,5,6) with 24 carts each one.



You may create and save infinite pages, called script files with extension ROT.



Exit -

New - clear selected page

Open - open a script file and load in the selected page;

Save as - save a script file and with a name with extension ROT;

Save - save again a script file with the same name.




Config - configurations

Log - see log files;


Color - load default colors;








EBRcart2 - show version and little help.



4) DISPLAY AND CONTROLS



-  play loaded audio
-  pause. Resume this point.
-  stop. Restart from beginning.
-  back 5 seconds.
-  forward 5 seconds



play next audio



eject loaded audio




repeat.




when MIX 1 +2 is not selected and you try play two audios. The second stay in wait mode.



progress bar . Click to alter position of play.




total time of audios in the page




- **AUTO:** automatic play next audio;
- **MIX 1 + 2:** allow play two audio at the same time;
- **FADE:** when you pres STOP, reproduction is finished with fadeout (time is configured)

Playing an audio in background (BG)

- During audio playback on channel 1, press REPEAT (disable AUTO, MIX 1 +2).
- When you press other button to play other audio, this audio is loaded on channel 2 and the volum of channel 1 is fade out to predefined level (you can change this level, in the next time the new level will be remembered). Time to fade is configurated (*fade to talk time*).
- At the end of audio in channel 2, the volum of channel 1 return to normal.





5) CARTS

Each cart is divided in 3 parts:

- an identification by number (1...24), letters (A...X) or functions keys (F1 ...F12);
- area for filename;
- duration of audio/video;

1	01. Pink Floyd - Comfortably Numb.mp3	10:02
2	02. Queen - Killer queen.mp3	03:01
3	03. Jimmy Hendrix - Purple Haze.mp3	02:53

← red = playing

← yellow = paused


← gray or other color = stopped

The carts can be coloured.


To select color for cart, right-click the number and select a color.



Or left-click the number and click the button .



Volum controls




adjust volum level for channel 1 and 2

MIC button



Press to fade volum of channels 1 and 2.

If you adjust volum controls after press this button, in the next time you use this control, your adjust will be remembered.



EJECT - left-click on identification of cart (it turn GREEN) and click this button to clean a cart. Right click on duration has the same effect;



COLOR - left-click on identification of cart (it turn GREEN) and click this button to color a cart. Right click on identification has the same effect;




CUE

Left-click on identification of cart (it turn GREEN) and click this buttons to cue.




windows for cue

6) REMINDERS



This area is to digit reminders or message to other monitor plugged in the same video-card using y-cable.


7) How search and select audio files:



Show or hide clock



counter of files



select to show files into subdirectory




show scripts files



= refresh the files list;




= write the part of filename to seek



= use to select files with names in the format “mmdd – description.mp3” where mmdd is equal month and day.

For example: 1022 – description.mp3 = news created at october, 22.



= show all files



= play the select file in the cue channel;



= expand your screen to right (>>) or down (V)

8) Loading carts

The carts are divided in 6 pages, selecte one of them clicking the buttons:



The page 1 is the initial selection. All of the cart on the screen are belonging this page.





a) Copying a file: method drag and drop

Select one file at the list and drag it to the cart and drop it;

One cart can be moved to other, right-click over cart and click on new cart.

b) Copying many files:

a. click the numeric button of the first cart to be load. The numeric button will be GREEN;




b. select the audio files to be copied and click the button

c. all the select files will be copied to the carts;

9) Reproduction (play)

Method 1: - left click the cart for reproduction.


Method 2: - move the mouse on the cart. The cart will be LIGHT YELLOW, press the space bar to play the audio.



Method 3: - if “buttons with letters” is selected, the numeric buttons will be replaced by letters A to X. Press this letters to play the audios.

Method 4 – if “buttons with function keys” is selected, the numeric buttons will be replaced by F1 to F12 and 0 to 9. Press this keys to play the audios.

The cart will be red:



Controls:

AUTO
 MIX1+2
 FADE

MIX1+2 = only one file will be played each one, avoiding erroneous mix.

MIX1+2 = allow play two audios at same time;

AUTO (MANUAL) : after play one audio, the next cart will be selected e only will be played when the user click the mouse ou press the space bar.

AUTO (AUTOMATIC): after play one audio, the next cart will be played.


10) REPRODUCTION WINDOWS



Clicking in this bar forward ou backward the audio.

Click the name to stop reproduction

PLAYING VIDEO CLIP



This window is displayed over the main window.

If you wish to show the video on a separate monitor, click **MONITOR** and select it.

Configure EBRcart2 to playback video through a dedicated Video Out connection (using or not a dedicated separate Video card) instead of on the PC monitor.

In television application, any images being output from EBRcart can go to a switcher and then over the air.

